



*Uninstall
Documentation*

V 6.0

Table of Contents

Windows NT: 3

UNIX: 3

FLEXLM Uninstall Documentation: 3

Windows NT: 3

UNIX: 4

Windows NT:

The uninstall removes the installation directory, the Start Menu shortcuts and registry entries set by IGES/Works. To run the uninstall, go to the add/remove programs under the control panel and double click on the IGES/Works entry in the list. Once these files are deleted, delete the uninstall_IGES/Worksv60.bat file in the temp directory and the uninstall is complete.

UNIX:

To uninstall IGES/Works, you must remove the install directory. Make sure that you have the proper permissions before attempting to remove the installation. Being root is suggested to do this.

```
EX: rm -rf <installation directory>
```

FLEXLM Uninstall Documentation:

Windows NT:

You will need Admin privileges to do this.

1. Stop lmgrd: To do this, go to your FlexLM directory, into the license directory and run the stop_license.bat.
2. To remove the NT service, try the following.
 - a: Go to where you installed FlexLM and Run LMTOOLS.ext from your license\nt directory. Click "Configuration using services" Highlight the service then click on the "Configure Services" tab at the top right. Press the "Remove Service" button and it should delete your service.
 - b: If the service does not show up in this list but is visible in the Windows NT "Services" control panel, go to configure services and type the name into the "Service Name" box as it appears in the Windows NT services panel. Then click "Remove Service".
3. Delete your flexlm directory, but make sure to save your license file if you still need it.

UNIX:

You will need to be root to do this.

1. Go to your location where you installed FlexLM, into the license directory and run `stop_license.csh`.
2. Delete your flexlm install directory and all items in it.
3. Remove the bootup files and code, see below for how to do this for each system.

IBM AIX:

Go to `/etc` and delete the `rc.itiohio` file. Open `Inittab` and remove the following lines.

```
#Following line added by IGES/Works 6.0 License installer.
```

```
#File created: mm/dd/yyyy
```

```
rcitiohio:2:wait:/etc/rc.itiohio > /dev/console 2>&1
```

Sun Solaris:

Go to `/etc/rc2.d` and delete the `S86itiohio` file.

SGI Irix:

Go to `/etc/init.d` and remove the `Itiohio` file. Then go to the `/etc/rc2.d` and remove the `S86itiohio` file.

HP-UX:

Go to `/sbin/init.d` and remove the `Itiohio` file. Then go to the `/sbin/rc2.d` and remove the `S86itiohio` file.